



ACCOUNT TITLE	ACCOUNT NUMBER	TRANSIT NUMBER	ROUTING NUMBER
		121301578	59-157/1213



### PRINTING THE CODE

The exact sequence of all magnetic characters is shown above. The common machine language must be printed in E-13B type with magnetic ink in accordance with Bank specifications.

### THE MICR BAND

An area 5/8" deep by 6" long is reserved for the common machine language characters. No other magnetic ink printing may appear in this area. Non magnetic ink may appear in the shaded area provided it does not extend into the 1/4" wide magnetic printing band reserved for the coded characters.

The check printing specifications contained here may be helpful to you when placing your order of personal checks. Please present these printing specifications to your printer.

## TO THE PRINTER:

Please note the check printing requirements outlined below. See personal check diagram on page 1.

**Transit Number:** The MICR encoding is 121301578 for all Central Pacific Bank branches. Place the Transit Number 121301578 in positions 34 through 42. Place the Transit Number symbol (⦿) in positions 33 and 43. See personal check diagram on page 1.

**Routing Number:** The routing number is 59-157/1213. Place the Routing Number near the upper right corner of the checks. See sample check below.

Lee M. Accountholder 1234 South Street Honolulu, Hawaii 96999	DATE _____	NO. <u>0001</u>
		59-157/1213
PAY TO THE ORDER OF _____		\$ _____
		Dollars
<b>CENTRAL PACIFIC BANK</b> P.O. Box 3590, Honolulu, HI 96811 808-544-0500   800-342-8422 (Toll-Free)   cpb.bank		
FOR _____		
⦿ 121301578 ⦿ 2120000106 ⦿ 0001		

**Check Serial Number:** This field is used for serially numbering personal checks. These numbers appear on the customer's account statements. Place the 4-character check serial number in positions 14 through 17. Right justify the serial number and left zero-fill as necessary.

**Deposit Tickets:** A mandatory transaction code of **10** is required in positions 15 and 16 on all **deposit tickets**. See personal check diagram on page 1. Please note that positions 15 and 16 are also used for check serial numbering purposes on **personal checks** only. See **Check Serial Number** paragraph above.

**Account Number:** The account number contains ten (10) characters. Place the account number in positions 21 through 31. Place the Dash symbol (⦿) in position 27. Also place the On-Us symbol (⦿) in position 20.

For example, Account Number 9876543210 is formatted as 9876⦿543210 ⦿

**Paper Size and Weight:** See personal check diagram on page 1 for minimum and maximum check sizes. The optimum paper weight is 24 lbs.

**Questions:** If you have any questions regarding Central Pacific Bank's personal check printing specifications, please contact your account officer or Central Pacific Bank's Customer Service Center at (808) 544-0500, Neighbor Islands at (800) 342-8433 (toll free).